



Sage Estimating (SQL) v19.12

Installation and Administration Guide

August 2020

This is a publication of Sage Software, Inc.

© 2020 The Sage Group plc or its licensors. All rights reserved. Sage, Sage logos, and Sage product and service names mentioned herein are the trademarks of The Sage Group plc or its licensors. All other trademarks are the property of their respective owners.

Last updated: August 31, 2020

Contents

Introduction	1
Conventions Used in this Document	2
Ways to Get Help	3
Training	5
Technical Assistance	6
Submitting Enhancement Requests	6
Chapter 1: System Overview	7
Sage Estimating Components	7
Configuration Tools in Sage Estimating	9
Chapter 2: System and Other Requirements	11
Access Rights	12
Supported Upgrade Path from Estimating (Pervasive)	14
Chapter 3: Installing and Configuring Sage Estimating	15
Installing on a Server / Workstation (Example)	16
A. Install Sage Estimating	17
B. Install and Configure SQL Server	18
C. Configure Your License Server (License Administration)	20
D. Connect Workstations to Your License Server (Configuration Wizard)	20
E. Connect Workstations to Your SQL Server Instance (Configuration Wizard)	21
F. Install Standard Databases and Migrate or Upgrade Your Data	22
G. Set Up Estimating Security	23
H. After You Complete Your Setup	26
I. Other Installation Scenarios	27
Technical note about the Common Language Runtime in SQL Server	28

Chapter 4: Data Migration	29
Overview	29
Changes in the Database Structure	29
Migrating Your Data	31
Sharing report layouts after migration	33
Chapter 5: Configuring SQL Server	34
Setting Up a SQL Server Instance for Use with Sage Estimating	34
Setting Up Security	37
Setting Firewall Exceptions	37
Additional Recommendations	40
Copying Databases from Other Instances	41
Chapter 6: Managing Your License	43
About the License Server and the Sage Online Licensing System	43
Estimating Modules and License Uses	43
General Licensing Steps	44
Designating a Sage License Server	44
Registering the Software and Activating Licenses	46
Connecting to the License Server from Sage Estimating	46
Updating License Information	47
Deauthorizing a License Server	47
Changing Your Company's Registration Information	48
Moving Your Sage License Server to Another Computer	49
Multiserver Licensing	49
Monitoring License Use	51
Checking Out a License for Offline Use	52
Troubleshooting License Server Issues	53
Windows "Sleep Mode" Prevents Computers from Obtaining a License Use	55
Index	57

Introduction

Sage welcomes you to Sage Estimating.

Read the supporting documentation carefully to make sure you understand the process before you install and configure Sage Estimating.

- This *Installation and Administration Guide* includes a system overview, installation and configuration instructions, and information about managing your Sage Estimating license.
- The *Release Notes* provide details about new features, database changes, known issues, and fixes.
- The *Getting Started Guide* provides an operational overview of the Sage Estimating software.
- The *SQL Server Guide* gives you an overview of the significant differences between the SQL Server databases and the Pervasive databases used in previous Sage Estimating releases.
- The *Sage 100 Contractor Integration Guide* describes how to integrate Sage Estimating with Sage 100 Contractor, making certain data in that program available in Sage Estimating, and it explains how to use the interface wizards to send proposals, budgets, and change orders you create in Sage Estimating to Sage 100 Contractor.
- The *Sage 300 Job Cost Integration Guide* provides installation, setup, and operating instructions for Sage 300 Job Cost integration.
- The *Means Integration Guide* provides installation, setup, and operating instructions for Means Integrator.
- The *On-Screen Takeoff Integration Guide* provides installation, setup, and operating instructions for Sage 300 Construction and Real Estate.

Notes:

- For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824>.
- Documentation for all supported versions of Sage Estimating (SQL) is available at <http://cdn.na.sage.com/Docs/en/customer/estimating/Documentation.htm>.
- Documentation for all supported versions of Sage 100 Contractor is available at <http://cdn.na.sage.com/docs/en/customer/100contractor/Documentation.htm>.

Conventions Used in this Document

This document uses the following conventions:

- Information you type into the software is shown in bold font. For example: Type **Miscellaneous** in the box.
- The names of screens, windows, fields, and other features displayed by the software are shown in **bold font**.
- Names of keys are also shown in bold font. For example: **Enter** or **Tab**. A plus sign (+) between two key names indicates you should press the keys simultaneously.
- The names of buttons you can click are shown in bold font and enclosed in brackets. For example: **[OK]** or **[Post]**.
- Variable names or names that are specific to your installation may appear in italics and brackets. For example: [*Drive*]\\[*Server*].

Notes, Tips, and Cautions

Note: This style shows that the information supplements the adjacent text.

Tip: This style indicates helpful points about using the software.

Caution! This style indicates important information to help you avoid a loss of critical data.

Important! This styles indicates critical information that you need to understand or important steps you need to take.

Menu Paths

In this document, menu paths show you the steps required to start a task. Menu paths appear in bold font with square brackets around buttons. For example:

"If the program does not automatically start, click **[Start] > Run**."

Ways to Get Help

Use Sage Estimating Help or a variety of self-help resources to get answers to your questions. You can also call Customer Support.

The Help System


Sage Estimating Help provides more efficient access to information than most manuals. With a click of the mouse or a keystroke, you can easily get Help for a command, a field, a window, or a procedure.

Sage Estimating displays Help in your default browser. If you have an Internet connection, it displays the most current Help for your version of Sage Estimating available from a hosted Help server. If you have no connection (you are working offline), it displays Help that was current when the software was released, and is installed on your computer when you install Sage Estimating.

Important! Because the Microsoft Edge browser does not display locally installed help properly, we recommend that you select a different default browser when working offline.

To get Help on a window option


To display Help for an option in a window, do one of the following:

- Click  **What's This?** on the toolbar or on the title bar, and then click the option.
- Select **What's This?** from the **Help** menu, and then click the option.
- Select the option, and then press F1.

To get Help for the whole window

For information about the window, such as the window's purpose and what tasks you can perform in it, click **[Help]** at the bottom of the window.


The Window Help Button



To use Help to learn how to do tasks

1.  Click [**Help**] on the toolbar, or select the **Home** tab > **Help** group > **Help** (or select **Help** menu > **Help topics** in classic view).

The Help Window



2. Use one of these tabs on the navigation pane to begin looking for a topic.
 - a. **Contents** contains Help subjects organized within books.
 - b. Click the **Glossary** heading on the Contents tab to view an alphabetical list of definitions of terms used throughout the Sage Estimating software.
 - c. **Index** contains an alphabetical list of Help subjects.


When you see the topic you want, double-click it to display it.

3. Use the **Search** box to find articles that match the keywords you enter.


Additional Self-help Resources

The Help menus available in ribbon view and in classic view provide convenient links to a variety of self-help resources.

The Help menu in Ribbon view



The Help menu in Classic view



Training


Sage University offers online and classroom training sessions to help you get the most out of your Sage Estimating software. To visit Sage University, go to www.sageu.com.

You can also click **File > Help > Sage University**.

Technical Assistance

When you need assistance, refer to the Knowledgebase article [How do I get technical support for Sage Estimating?](#) to determine which service works best for you.

Submitting Enhancement Requests

We want to hear your suggestions for improving the software. To send us your comments, click the File menu button  and then select **Help > Submit Product Idea**.


Chapter 1: System Overview

Before you can run Sage Estimating, you need to activate your license, and install and configure the components on which the Estimating system relies.

This chapter provides an overview of the Sage Estimating system, including:

- Installed components
- Tools you use to configure your system after installation
- The Sage online licensing system

Sage Estimating Components



Your On-Premise Sage Components

Your Sage Estimating system includes these components:

- Your purchased Sage Estimating applications
- Your Sage license server
- Your SQL Server instance

You can set up these components on a single machine or on multiple machines. You choose the configuration that best meets your needs.

Sage Estimating must be able to communicate with both your license server and your SQL Server Instance.

The Sage Estimating application

The Sage Estimating application is the main component of the Sage Estimating suite of programs. It includes the Sage Estimating Configuration Wizard, which you use to connect Sage Estimating from each workstation to your license server and to your SQL Server instance.

When it is connected to your Sage license server, Sage Estimating:

- Acquires a license use while you have it open.
Sage Estimating must maintain a connection to your Sage license server.
- Releases the license use when it is closed.

Your License Server

Your Sage license server communicates with the Sage online licensing system. It performs the following tasks:

- It obtains licenses from Sage for your purchased products based on your registered Company name and Sage Client ID, which must exactly match the Company name and Sage Client ID in your account.
- It provides available license uses to your networked Sage Estimating computers.

Because it attempts to connect periodically to Sage, the license server must have continuous Internet access.

Your SQL Server Instance

Your SQL Server instance serves up, stores, and processes Sage Estimating data (including estimates, standard databases, address book, and so on).

The Sage Online Licensing System

Sage Estimating uses a convenient online system to activate and verify your Estimating license.

The Sage online licensing system resides at Sage, and it:


- Maintains a list of your purchased modules and number of license uses.
- Provides information to your Sage license server (at your company) about the modules and license uses to which your company is entitled.

You use the License Administration window to connect to the Sage online licensing system. When you submit your registered Company name and Sage Client ID to Sage, the Sage online licensing system determines the number of license uses and the features that your purchased license provides, and it allocates the licenses to your license server for use in your environment.

Configuration Tools in Sage Estimating

After installation, you use the following configuration tools to set up Sage Estimating:

- **License Administration.** You use the License Administration window to allocate your product licenses and license uses to your designated Sage license server. For more information, see "Activate your license on the Sage license server" (page 20) and "Managing Your License" (page 43).
- **Configuration Wizard.** You use the Configuration Wizard to connect each workstation to the designated Sage license server and SQL Server instance. For more information, see "D. Connect Workstations to Your License Server (Configuration Wizard)" (page 20) and "D. Connect Workstations to Your License Server (Configuration Wizard)" (page 20) in Chapter 3—Installing and Configuring Sage Estimating.
- **Estimating Management Console.** You use the Estimating Management Console to manage your SQL databases, estimates, custom reports, contacts, and security.



Chapter 2: System and Other Requirements

Before you install Sage Estimating, you should:

- Confirm your registration information:
 1. Log into the Sage Customer Portal at:
<https://customers.sagenorthamerica.com/>
 2. Confirm that the Company name used to register your Sage Estimating software exactly matches the Company name used to activate your standard database.
 3. If these names do not match, contact Customer Support before you install and activate Sage Estimating.

Important! This step is particularly important if you are upgrading from a version prior to version 17.11, when the registration information may have been slightly different. If these names do not match, you will not be able to reactivate your database.

- Ensure that your system meets the minimum hardware and software requirements.

As with any software, as we continue to enhance Sage Estimating, you will realize optimal system performance by using up-to-date computer hardware (memory as well as overall hardware specifications).

For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824>.

For help in selecting the right business-class computers for your business-class software, contact your authorized business partner.

- Ensure that you have sufficient Windows permissions to install the software.

If you are upgrading from an earlier version of Sage Estimating, or you plan to use an existing SQL Server instance, you must also have sufficient permissions on the SQL Server instance.

For more information, see "Access Rights" (page 12), later in this chapter.

- If you are upgrading from an earlier version of Sage Estimating, make sure you are upgrading from

a supported version of the product.

For more information, see "Supported Upgrade Path from Estimating (Pervasive)" (page 14), later in this chapter.

Access Rights

The following sections describe the access rights you need to install and use Sage Estimating.

Elevate Permissions

During installation, you may be prompted to elevate your privileges. If you do not acknowledge each message within two minutes, the installation process will quit the task. If this occurs, you may receive a separate message asking you to retry the task. To retry the task, click **[Retry]** and then elevate your privileges when prompted.

SQL Server Permissions

Always use the **Security** feature in the Estimating Management Console to configure security for Sage Estimating.

Important! Do not use SQL Server Management Studio to modify security settings.

For more information on setting up SQL Server security for Sage Estimating, see "G. Set Up Estimating Security" (page 23).

Full Control of Specific Files and Folders Required

To use Sage Estimating, you must have full control of the following files and folders on your file server, terminal server, and workstations that have Sage Estimating installed. Make sure that your system administrator also gives you full control of all the subfolders and files.

Caution! Incorrectly modifying Microsoft Windows security may severely impair your system operations. Sage is not responsible for operation problems caused by incorrectly modifying your Microsoft Windows security settings. To set permissions on your network or Windows operating system, you must have advanced knowledge of your network. Contact your system administrator for assistance.

Folders and Files Requiring Operator Control

Product	Operating Systems	Required Folders and Files	Location and Specifications
Sage	64-bit Windows	[Drive]:\Program	This folder is located on the file

Product	Operating Systems	Required Folders and Files	Location and Specifications
Estimating	systems	Files (x86)\Sage\Estimating	server, terminal server, and workstations where you installed Sage Estimating. It is the default installation location for Sage Estimating. However, depending on your system configuration, your company may have renamed this folder or installed it to a different location.
Sage Estimating	Windows 7, Windows 8.1, Windows 10	[Drive] :\Users\Public\Sage\Estimating -and- [Drive] :\ProgramData\Sage\Estimating	These folders are located on the workstation or terminal server where you use Sage Estimating. Sage Estimating installs necessary files to these folders and requires that the user has full control of them.

Note: Some of these folders may be hidden. To view them:

- **In Windows 7:** Open Windows Explorer, and then click **Organize> Folder and Search Options> View tab > Show hidden files and folders**.
- **In Windows 8.1 and Windows 10:** Open Windows Explorer, click the **View** tab, and then select the **Hidden items** check box in the **Show/hide** group.

Full Control and Read Access to Specific Registry Keys Required

To use Sage Estimating, you must have full control of the following Windows registry key on your file server, terminal server, and workstations that have Sage Estimating installed. Make sure that your system administrator also gives you full control of all subkeys.

- HKEY_CURRENT_USER

You should also have read access to the following registry keys and associated subkeys:

- HKEY_Local_Machine\Software\ODBC
- HKEY_Local_Machine\Software\Wow6432Node\Sage

Caution! Incorrectly editing the Microsoft Windows registry may severely damage your system. Sage is not responsible for damage to your system caused by editing the registry. Before making changes to the registry, contact your system administrator for assistance and make a backup copy of all valued data.

System administrators, see Microsoft Registry Editor Help topics for detailed instructions.

Supported Upgrade Path from Estimating (Pervasive)

If you plan to use your estimate data from a release earlier than version 9.6, you must upgrade your data to Sage Estimating 9.6 or later prior to migrating your data. Refer to "Data Migration" (page 29) for data migration instructions.

You can upgrade any Windows-based Sage Estimating data (beginning with Sage Estimating 1.0) to Sage Estimating 9.6.

If desired, you can install this version of Sage Estimating without uninstalling your previous Sage Estimating installation. However, because the data format is different, you cannot migrate data to this release from releases of Sage Estimating earlier than version 9.6 without upgrading your data first.

Chapter 3: Installing and Configuring Sage Estimating

You can set up Sage Estimating in any of the following configurations:

- On a server/workstation domain
- In a workgroup environment
- On a standalone computer

The server/workstation configuration is a common setup where multiple Sage Estimating workstations access the same SQL Server instance and Sage license server. The next sections step you through the installation and configuration of a Sage Estimating system in a server/workstation domain, highlighting the distinct components of the system. However, you are not limited to this configuration.

Tip: For information on the other supported configurations of Sage Estimating, see "I. Other Installation Scenarios" (page 27).

Before You Install or Upgrade Sage Estimating

- Read and understand the information in this guide.
- If you are currently using a previous version of Sage Estimating, create a complete backup copy of all Sage Estimating data and program files before installing this version.
- If you are installing Sage Estimating on a new computer, make sure that .NET 3.5 is enabled.
- Install the appropriate operating system service pack, make sure that there is sufficient hard disk space available, and ensure that your server and workstations meet all other hardware and software requirements.

For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824>.

- Make sure that you have full control of the necessary folders, files, and registry keys on your file server, terminal server, and workstations that will have Sage Estimating installed.

For a list of the required folders, files, and registry keys for your operating system, see the chapter on "System and Other Requirements" (page 11).

- Close all programs and services for the duration of the installation. This includes programs that may be running in the background such as antivirus, email, and backup programs.
- Decide which installation scenario to follow.
See "Configuration Tools in Sage Estimating" (page 9).
- You must have the appropriate permissions to perform certain tasks described in this chapter. Contact your Sage Estimating administrator if you require additional permissions.

Installing on a Server / Workstation (Example)

A server/workstation configuration uses separate machines for:

- The SQL Server (which hosts Estimating databases)
- The Sage license server (from which you administer licenses)
- One or more Sage Estimating workstations (where you use the Estimating programs to create estimates and do related processing)

To install and configure Sage Estimating on a server/workstation setup, you perform the following general steps:

Note: For details on each step, refer to the associated sections indicated in parentheses for each step.

1. **At the SQL Server machine,** install and configure the SQL Server Instance (Section B)
2. **At the license server machine:**
 - a. Install Sage Estimating (Section A)
 - b. Configure your license server (Section C)
3. **At the workstation or server where you will host your Sage Estimating data:**
 - a. Install Sage Estimating (Section A)
 - b. Connect to the Sage license server (Section D)
 - c. Connect to SQL Server (Section E)
 - d. Install standard databases and migrate your data from Estimating (Pervasive) if necessary, or upgrade your data (Section F)

Note: You only do this step once, from a single workstation, because the data is hosted on the SQL Server instance and shared by all workstations.

- e. Set up roles and permissions (Section G)

4. At each Sage Estimating workstation:

- a. Install Sage Estimating (Section A)
- b. Open Sage Estimating to verify that the workstation can connect to the license server and SQL Server instance.

A. Install Sage Estimating

If you have not already done so, download the Sage Estimating installation files according to the instructions provided in the software notice. If you are installing Sage Estimating on a server, ensure you save the installation files in a location that all workstations can access. Then copy the installation files to each workstation where you want to install Sage Estimating.

Note:

- The installation process may restart your computer during the installation. Ensure you close all programs and applications before starting the installation to avoid losing any data. If your computer restarts, log on to your computer again.
- If you choose to upgrade data from a previous version of Sage Estimating, the process may take up to four hours, depending on the size of your databases. Plan accordingly.

Important!

- Do not install Sage Estimating unless you have sufficient hard disk space available.
- For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824..>
- Do not install previous releases of Sage 300 Construction and Real Estate after installing Sage Estimating. The new licensing system is incompatible with previous releases.

1. At the workstation or server, log on with full administrative rights.

Full administrative rights means write access to the Windows registry and all folders on the computer (including rights to the root of all hard drives). If you are unsure whether you have full administrative rights, ask your network administrator for assistance.

2. Double-click the **SetMeUp.exe** file in your local Sage Estimating **Install** folder.

The Sage Estimating **Install** folder is at the location you specified during the Sage Estimating download process. For example, if you downloaded the installation files to C:\Users\Public\Public Documents\Sage Estimating, look in this folder for the **SetMeUp.exe** file.

3. When prompted by the **User Account Control** dialog box, click **[Yes]** to allow the program to make changes to the computer.
4. Read the terms of the Sage License Agreement, and then click **[Accept]** to accept them.
5. On the Sage Estimating installation window that appears, select **Install Sage Estimating**.

Selecting this option alone installs the Sage Estimating software and support components.

If you are installing Sage Estimating only for demonstration or trial purposes, or if you are configuring Sage Estimating for a single user, SQL Server Express may be adequate. However, for large databases and multi-user configurations, Sage strongly recommends implementing your Sage Estimating system with a standard version of SQL Server.

6. Follow the remaining steps as prompted by the installation process, which guides you through the installation of Sage Estimating products and required support software.
7. Repeat steps 1 through 6 for each workstation or server where you want to install Sage Estimating.

B. Install and Configure SQL Server

If you are installing Sage Estimating for the first time or if you want to create a new SQL Server Instance, install or configure a supported version of SQL Server on the computer on which you installed Sage Estimating. Refer to the *Sage Estimating SQL Server Guide* for information about installation and the SQL Server settings that Sage Estimating requires.

If you want to use an existing installation of SQL Server, refer to "Configuring SQL Server" (page 34) for settings for creating and configuring a new instance.

If you need to create a new SQL Server instance, you can select the **Create a new local SQL Server instance** option during installation. This option will install a new instance of SQL Server Express 2014.

Important! If you are using Sage Estimating in a multi-user environment, Sage recommends that you use the standard SQL Server product. Although SQL Server Express is a reasonable choice for smaller-scale implementations, it does not support databases larger than 10 GB and can only use 1 GB of RAM (among other limitations), so we do not recommend that you use it for a shared SQL Server instance.

If you are operating in a workstation/server environment (see "Installing and Configuring Sage Estimating" (page 15)), you do not need to install SQL Server on the workstations.

Important! To allow communication with a remote SQL Server instance, you may need to set firewall exceptions for the SQL Server Database Engine and the SQL Server browser services. If your firewall blocks network traffic between your computer and the SQL Server instance, you will not be able to connect workstations to the server. For information about setting these exceptions, see [Setting Firewall Exceptions](#).

Notes:

- At the instance name prompt, type a name for the new SQL Server instance (database server) in the box, and then click [OK].

The default instance name is **SAGE_ESTIMATING**, but you can give the instance any name you want provided you do not give it the same name as any existing SQL Server instance on the computer.

- SQL Server allows an unlimited database size. However, SQL Server Express limits the database size to 10 gigabytes (GB). Sage Estimating warns you if your database size nears the limit.

If you select the option to create a new SQL Server instance in the Select installation options for Sage Estimating window, the installation process automatically configures a new Sage Estimating-compatible instance for you.

- If you plan to migrate existing data from Pervasive-based Sage Estimating (version 9.6 and later) to version 19.12, you must install SQL Server on the destination computer or server.
- The installation process may restart your computer. If your computer restarts, log back onto your computer at the prompt.
- You can install an approved instance of SQL Server side by side on a computer where other versions of SQL Server are installed. Be aware that installing Sage Estimating may result in an "Install completed with errors" message. However, the resulting Sage Estimating installation operates correctly.

Caution! Sage recommends *against* installing SQL Server on a domain controller. Installing SQL Server on a domain controller is a security risk, and not recommended or supported by Microsoft.

For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824>.

C. Configure Your License Server (License Administration)

Before configuring your license server

Make sure you have an active Internet connection.

Activate your license on the Sage license server

To activate your license:

1. On the machine designated as your license server, open the **License Administration** window.

Click **Start > All Apps > Sage Estimating > License Administration**.

2. Check that computer named in the **License server** box is the designated license server.

If License Administration is not pointing to the correct server, click **Change server**, and then enter the correct computer name or IP address of your license server.

3. In the Registration Information section, submit your registration details as follows:

- a. Click the **Edit registration information** link.
- b. In the **Sage client ID** box, type your client number.
- c. In the **Registration name** box, type your registered company name exactly as provided by Sage.
- d. Click **[OK]**

If the activation was successful, the Licensed Modules grid displays the modules and number of uses that you have purchased. Your license server is now ready to serve licenses to your Sage Estimating (SQL) users.

If the activation was successful, the Licensed Modules grid displays the modules that you have purchased.

For more information, see "Managing Your License" (page 43).

D. Connect Workstations to Your License Server (Configuration Wizard)

Note: You perform these steps on each workstation that will run Sage Estimating.

The Configuration wizard is installed automatically during Sage Estimating installation.

To connect to your Sage license server

1. Start the Configuration wizard as follows, depending on your operating system:
 - **For Windows 7:** Click **Start > All Programs > Sage > Estimating 19.12 > Configuration Wizard**.
 - **For Windows 8.1 or Windows 10:** Click the **Configuration Wizard** tile on the Start menu, or right-click outside the tile area, and then click **All apps > Sage > Configuration Wizard**.

Important! Depending on your version of Windows, you may need to elevate your permissions before starting the Configuration wizard. On the Start menu, right-click **Configuration Wizard**, and then select **Run as administrator**.

2. In the navigation pane of the Configuration Wizard, click **Licensing**.
3. In the right-hand pane, select the **License Server** option, and then click **[Change]**.
4. In the **Specify License Server** window that opens:
 - a. In the **Computer** box, enter the name of the computer running the license server.
 - b. In the **Port number** box, ensure that the port is set to **48650**.
 - c. Click **[OK]**.

Note: A green check mark appears beside the Licensing item in the navigation pane if you connected to the license server successfully.

For more information, see "Managing Your License" (page 43).

E. Connect Workstations to Your SQL Server Instance (Configuration Wizard)

Note: Before connecting workstations to your SQL Server instance, make sure that the SQL Server instance and your browser can communicate with other machines on your network. If your firewall settings are blocking communication with your server, the Configuration Wizard cannot find the SQL Server instance. For more information, see [Configuring SQL Server](#).

As a final step in configuring the workstation, connect to the SQL Server instance ("server"), as follows:

1. Start the Configuration wizard as follows, depending on your operating system:
 - **For Windows 7:** Click **Start > All Programs > Sage > Estimating 19.12 > Configuration Wizard**.
 - **For Windows 8.1 or Windows 10:** Click the **Configuration Wizard** tile on the Start menu, or right-click outside the tile area, and then click **All apps > Sage > Configuration Wizard**.
2. In the navigation pane of the Configuration wizard, click **Data Server**.
3. Beside the **Server** box, click **[Select]** (or click **[Change]** to select a different instance).

The Select a SQL Server window appears.

4. In the **Server** box, type the name of the computer that is hosting your SQL Server instance.

Tip: If you are not sure of the name, click **[Search]**, and then select the server from the list.

5. Click **[Verify]**.

A green check mark beside the Data Server item (in the navigation pane) indicates a successful connection to your SQL Server Instance.

6. Click **[Close]** to exit the Configuration wizard.

For more information, see "Configuring SQL Server" (page 34).

F. Install Standard Databases and Migrate or Upgrade Your Data

If you have existing Pervasive-based estimate data, you can migrate your data to the current Sage Estimating version. If you are upgrading from an earlier version of Sage Estimating (SQL), you must upgrade your data before you can work with it in the current version. You can also install any standard (industry) databases that you have purchased.

If you have been maintaining your own items list that you want to continue to use, you can install a "shell" database that comes with Sage Estimating so that you don't have to set up your own database from scratch. These databases contain CSI industry phases codes, but no items. After installing a shell database, you enter an item list manually, or you can import items from an Excel spreadsheet.

You can perform these processes from any computer that has access to the SQL Server instance where you plan to store your estimate data.

Install standard databases

If you have purchased standard databases, you can install and activate them when you finish setting up Sage Estimating (SQL). You install Standard databases using the Estimating Management Console.

1. In the Estimating Management Console, click the **Standard DB** tab.
2. On the toolbar, click **Install Databases**.
3. From the dropdown list, select **Optional Databases**, and then double-click each standard database you want to install from the Available Databases pane.

Alternatively, if you want to install one of the shell databases (with no items, only phases), select **Shell Databases** from the dropdown list.

4. In the **Databases to install** box, type the activation code for each standard database. (The activation code must match your registration name exactly.)

Note: Shell databases that come with Sage Estimating do not have activation codes.

5. Click **[Install]**.

Migrate your data from Sage Estimating (Pervasive)

If you are upgrading from Sage Estimating (Pervasive) version, you can migrate your data directly to Sage Estimating (SQL). See "Data Migration" (page 29) for instructions.

Upgrade your data from an earlier version of Sage Estimating (SQL)

If you are upgrading from an earlier version of Sage Estimating (SQL), the Configuration Wizard will prompt you to upgrade your data when you start that application. Follow the steps in the wizard to complete the upgrade.

G. Set Up Estimating Security

There are two aspects to security in Sage Estimating: feature security and estimate security.

As a Sage Estimating administrator, you manage security by maintaining users, roles, and permissions on the Security tab of the Estimating Management Console.

Note: At least one operator must be assigned to the administrator role at all times. Typically, the person who installs SQL Server is the first Sage Estimating administrator. That person can then assign roles and permissions to others.

- If you install SQL Server as part of the Sage Estimating installation, you are automatically assigned the administrator role.
- If you install SQL Server outside the Sage Estimating installation process, you should assign yourself or another user to the **sysadmin** role for the instance.

About feature security

Important! Only a Sage Estimating administrator can set up and manage roles and permissions.

In the Security window, you use the Users tab to add Estimating users and the Roles tab to assign predefined roles to those users. Each role is associated with certain types of permissions. By assigning different roles to users, you control who can:

- Change estimate security
- Create estimates
- Edit a shared catalog
- Edit a standard database
- Manage custom reports
- Manage shared layouts
- Run the Management Console
- View databases and allow takeoff

About estimate security

Important! Only administrators and users who have **Change estimate security** permission can modify estimate security.

By default, all users can view and edit your estimates. If you want to restrict access to estimates, you must turn off the **Allow all users to view and edit all estimates** option on the Estimates tab in the Security window.

You grant View and Edit access individually for each estimate and for each user.

Setting up roles and permissions

Setting up roles and permissions involves the following general steps:

1. Adding roles and assigning features.
2. Adding users and assigning roles.

To add roles and assign features:

1. Start the Estimating Management Console.
 - **For Windows 7:** Click **Start > Programs > Sage Estimating 19.12 > Estimating Management Console**.
 - **For Windows 8.1 or Windows 10:** Click the **Estimating Management Console** tile from the Start menu, or right-click outside the tile area, and then click **All apps > Sage Estimating Management Console**.
2. In the Estimating Management Console, click [**Security**].
3. In the Security window, click the **Roles** tab.
4. Click [**Add**] to open the Add Role window.
5. In the Add Role window:
 - a. In the **Name** and **Description** boxes, type a name and description for the new role.
 - b. In the **Select Features for Role** box, select feature permissions that comes with this role.
6. Click [**OK**].

To add users and assign roles:

1. Start the Estimating Management Console.
 - **For Windows 7:** Click **Start > Programs > Sage Estimating 19.12 > Estimating Management Console**.
 - **For Windows 8.1 or Windows 10:** Click the **Estimating Management Console** tile from the Start menu, or right-click outside the tile area, and then click **All apps > Sage Estimating Management Console**.
2. In the Estimating Management Console, click [**Security**].
3. In the Security window, click the **Users** tab.
4. Click [**Add**] to open the Add User window.
5. In the **Add User** window:
 - a. In the **User Id** box, select the user you want to add from the list, or search the network for the user.
 - b. In the **Role** box, select the role that you want to assign to this user.
6. Click [**OK**].

Note:

- If you know the user Id you're trying to add, key it into the User Id field and select the role you'd like to assign to that user.
- If you don't know the User Id, you can click [Search] to retrieve a list of domain users (and groups) to choose from.
- Depending on your domain user count, the search method could take some time.
- Selecting a User Id will add that user. Selecting a Group Id will add all users contained in that group.

Managing Security

You can manage the user / role relationship using either the User tab or the Role tab. Changes you make on one tab are reflected on the other tab .

You can manage estimate security permissions from the Estimates tab, as well as the Estimate Info window if you have **Change estimate security** permission.

H. After You Complete Your Setup

Restart all programs and services that you shut down for the installation.

The Sage Estimating software performs a series of checks the first time you start it. If the Sage Estimating software notifies you of any error conditions, correct the condition before continuing.

Supporting documentation for Sage Estimating is available at <http://cdn.na.sage.com/Docs/en/customer/estimating/Documentation.htm>, or by clicking **Help > Product Documents** on the ribbon in Sage Estimating. These documents are in Adobe Acrobat (PDF) format. If you do not already have Adobe Acrobat or Acrobat Reader, you can download Adobe Acrobat from www.adobe.com.

Important! For performance reasons, if you plan to run a virus scanner on the machine that hosts the SQL Server instance, you should exclude files that have MDF, LDF, NDF, BAK, TRN, and TRC extensions. You should also exclude additional processes for the version of SQL Server that you are running. For more information about the files and processes to exclude, see Microsoft Knowledgebase article 309422 at <http://support2.microsoft.com/kb/309422>.

I. Other Installation Scenarios

Workgroup environment (multiple workstations connected to one computer that stores Estimating data and acts as License Server)

At the server machine:

1. **At the server machine:**
 - a. Install Sage Estimating (Section A)
 - b. Install and configure the SQL Server Instance (Section B)
 - c. Configure your license server (Section C)
2. **At each Sage Estimating workstation:**
 - a. Install Sage Estimating (Section A)
 - b. Connect to the Sage license server (Section D)
 - c. Connect to SQL Server (Section E)
 - d. Install or migrate and upgrade your data (Section F)

Note: You only do this step once, from a single workstation or on the server machine, because the data is hosted on the SQL Server instance and shared by all workstations.

- e. Set up roles and permissions (Section G)

Standalone workstation environment (a single workstation that stores Estimating data and acts as License Server)

At the standalone workstation:

1. Install Sage Estimating (Section A)
2. Install and configure the SQL Server Instance (Section B)
3. Configure your license server (Section C)
4. Connect to the Sage license server (Section D)
5. Connect to SQL Server (Section E)

6. Install or migrate and upgrade your data (Section F)
7. Set up roles and permissions as needed (Section G)

Terminal Server

Follow the steps for "Workgroup environment (multiple workstations connected to one computer that stores Estimating data and acts as License Server)" (page 27), with these exceptions:

- Always use **Add or Remove Programs** to start an installation to a terminal server.
- If you use another server to host Sage Estimating databases, install only Sage Estimating products to the terminal server.

Technical note about the Common Language Runtime in SQL Server

Beginning with version 18.11, Sage Estimating no longer uses the Common Language Runtime (CLR) integration feature in the Microsoft SQL Server instance, resulting in improved security and performance, and a more future-proof application. For this reason, the CLR integration feature is not automatically turned on for new installations of Sage Estimating.

When you upgrade from earlier versions of Sage Estimating, however, the upgrade process does not turn off the CLR integration feature. This means that the CLR integration remains turned on for your SQL Server instance. If you do not use the CLR integration feature in SQL Server and you have database security concerns, you should consider turning off this feature.

For instructions on turning on or turning off CLR integration for Microsoft SQL Server, see *Enabling CLR Integration* in the Microsoft developer's library at [https://technet.microsoft.com/en-us/library/ms131048\(v=sql.105\).aspx](https://technet.microsoft.com/en-us/library/ms131048(v=sql.105).aspx).

Chapter 4: Data Migration

If you have been using a Pervasive-based version of Sage Estimating, you can migrate (transfer) your existing Pervasive-based data to the Microsoft® SQL Server® database platform if you want to use it with this release.

Note: You must be using Sage Estimating 9.6 or later to migrate your data.

Overview

The process of migrating or making your existing Sage Estimating data compatible for use with the new Sage Estimating is performed using the data migration feature of the Estimating Management Console. This feature performs two functions when you select a Pervasive database for migration:


- Validates your existing data for compatibility with Microsoft SQL Server.
- Migrates or creates new SQL Server tables with your Sage Estimating data.

The Estimating Management Console performs these steps together when you start the data migration process. When you migrate your Pervasive databases, the Estimating Management Console creates corresponding .mdf and .ldf files in the specified SQL Server instance.

Changes in the Database Structure

Whereas Pervasive allows you to arrange your estimates in a hierarchical folder structure within each database, Microsoft SQL Server stores all your estimates in just one estimate database. It also stores your standard database and Address Book information separately.

Comparison of Pervasive and SQL Server



If you arranged your estimates in Pervasive folders and subfolders, the Estimating Management Console attempts to re-create the arrangement using "branches" in place of folders. These branches are for organizational display purposes only. They do not change the structure of your SQL Server database.

During the migration process, the Estimating Management Console may rename some of your database files to comply with SQL Server requirements. For more information on renaming database files, refer to the Estimating Management Console Help.

Migrating Your Data

1. Start the Estimating Management Console (select **Start > All Programs > Sage > Sage Estimating > Estimating Management Console**).
2. From the Estimating Management Console, click **[Data Migration]**.
3. Select step **2—Settings** in the Data Migration window.

- a. Click **Pervasive** (left-hand pane).

The Estimating Management Console checks your Pervasive databases and verifies they meet data migration prerequisites. If the databases do not meet the prerequisites, the Estimating Management Console displays one or more error messages.

- b. Correct each error condition, if any, and then try the verification process again by clicking **[Reverify]**.

- c. Click **[Options]**, and then:

- Select **Enable detailed logging** if you want to generate detailed entries in the Migration event log.

To prevent detailed migration event logging, clear the check box.

Note: Enabling detailed logging may slow the data migration process.

- Select **Allow non-administrators to view and edit migrated estimates** if you want to grant security rights by default to all users for the migrated estimates.

To prevent users other than administrators from viewing and editing the migrated estimates, clear the check box .

After migration, you can change which estimates users can view and edit in the **Security** section of the Estimating Management Console.

4. Click step **3—Select Databases**.

- a. Click **[Browse]**, and then locate and select the data folder that contains the Pervasive data you want to migrate.

To migrate layouts, browse to the Options folder that contains the report layouts or spreadsheet layouts you want to migrate.

- b. Click **[OK]**.

The **Data Migration** window displays the path to the selected folder in the **Starting folder** box.

The Sage Estimating scans the selected folder for all Pervasive databases that are available for migration, and then displays them in a list below the **Starting folder** box.

Note: The Estimating Management Console does not scan backup data folders (**PEBackup** folders). If the Estimating Management Console is unable to locate certain Pervasive databases, the databases may be residing in a PEBackup folder. Try renaming the PEBackup folders and restart the scan.

Tips: If desired, you can click the arrow key to the right of the **[Browse]** button, and then perform one of the following actions:

- **Cancel scanning.** Select this option to stop the scan at any time. The scan process can be lengthy, depending on the number and size of the files within the selected folder.
- **Rescan.** Select this option to scan the selected folder again.

- c. Select the check box for each Pervasive database in the list that you want to migrate.

You can select estimates, Address Book, and standard databases for migration.

If you are migrating layouts, select the **OptionsFile** check box, and then select **Spreadsheet Layouts** and/or **Report Layouts** as needed.

Important! To preserve links between estimates and standard databases, Sage recommends migrating your estimates concurrently with (or after) your standard databases. Migrating estimates before or separately from their standard databases breaks any links with their associated standard databases and disables certain editing functions in the spreadsheet.

5. Click **[Migrate]** to begin the migration process.

The migration process may take some time, depending on the size of the databases you are migrating. You can view the status of the migration from the migration event log by clicking step **4—Event log**.

Notes:

- If desired, you can also select other Pervasive databases for migration by repeating steps 3-5. Any additional migration jobs you schedule are placed in a queue and performed in order.

- Ensure you select the **Queued** check box at the top of the migration event log to see a list of pending migration jobs in the queue.
- Do not attempt to access any of the databases you are migrating until the migration process is finished. You cannot access a database while it is migrating.

6. Repeat steps 3 through 5, as necessary, to migrate all Pervasive databases you want to use with Sage Estimating (SQL).

Important! Report layouts and spreadsheet layouts are migrated to your personal layouts folder. Therefore, each Estimating user must migrate their own personal layouts.

If any of the migrated layouts were shared in Estimating (Pervasive) and should be shared in Estimating (SQL), you need to share the layouts separately for each type of report.

Sharing report layouts after migration

Sharing report layouts after migration is straightforward, but could take some time, depending on how many layouts you need to share with Estimating (SQL) users, and the number of users who need to share personal layouts.

To share a report layout in Estimating (SQL):

1. Open the report printing window (for example, on the ribbon, click Spreadsheet).
2. Click **[Report Options]**.
3. In the Report Options window, click **Manage Layouts**.
4. In the Report Layouts window, on the **My Layouts** tab, select each report layout you want to share, in turn, and then click **[Create Shared]**.

Chapter 5: Configuring SQL Server

Follow the instructions in this section to install and configure a SQL Server instance manually for use with Sage Estimating.

Important! If you are using Sage Estimating in a multi-user environment, Sage recommends that you use the standard SQL Server product. Although SQL Server Express is a reasonable choice for smaller-scale implementations, it does not support databases larger than 10 GB and can only use 1 GB of RAM (among other limitations), so we do not recommend that you use it for a shared SQL Server instance.

For current information about supported operating systems, Internet browsers, Microsoft® SQL Server®, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 101824, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=101824>.

Setting Up a SQL Server Instance for Use with Sage Estimating

If you already use a supported version of Microsoft SQL Server, you can set up another instance to work with Sage Estimating. (Options described in this section may vary slightly depending on the version you are installing.)

Note: If you choose to uninstall your existing instance first, restart your server before reinstalling to avoid problems with the new installation.

Caution! Do not change the owner of any databases in the Sage Estimating instance.

Configure your new SQL Server instance using the settings outlined in the following sections.

Named Instance

Instance Configuration Settings

SQL Server 2014 Setup

Instance Configuration

Specify the name and instance ID for the instance of SQL Server. Instance ID becomes part of the installation path.

License Terms
Global Rules
Product Updates
Install Setup Files
Install Rules
Feature Selection
Feature Rules
Instance Configuration
Server Configuration
Database Engine Configuration
Feature Configuration Rules
Installation Progress
Complete

☐ Default instance
☒ Named instance:

Instance ID:

SQL Server directory: C:\Program Files\Microsoft SQL Server\MSSQL12.SAGEEST

Installed instances:


Instance Name	Instance ID	Features	Edition	Version
<Shared Compone...		Tools, Tools\Tools...		9.4.5000

< Back Next > Cancel Help

You must use a named instance. You can give the instance any name you want. However, if you have installed a previous version of Sage Estimating (such as version 11.2), give the new instance a different name that is easily recognizable (such as SAGE_EST_19_11).

Authentication Mode

Authentication Mode Settings



The instance must support **Mixed Mode** authentication (**Windows Authentication and SQL Server Authentication**). This means either Windows authentication or SQL Server authentication can be used to access the database information.

When you use Windows authentication, the operator requires permission to use SQL Server or be a member of a group that has permission. In Windows authentication mode, SQL Server validates the account name and password using information from the Windows operating system.

When you use SQL Server authentication, the operator requires system administrator (**sysadmin**) rights in SQL Server. SQL Server authentication is used for backwards compatibility and requires a strong password.

Collation Settings

Collation settings must be **Latin1_General**, **case-sensitive**, and **accent-sensitive** (**Latin1_General_CS_AS**).

You customize the collation settings during the server configuration portion of the SQL Server installation. In the SQL Server collation customization window, make the following selections:

1. Select the **Windows collation designator and sort order** option (instead of **SQL collation**, which is the default):
 - **Latin1_General** (for the collation designator)
 - **Case-sensitive**
 - **Accent-sensitive**
2. Clear all other options.

Setting Up Security

You use the **Security** feature in the Estimating Management Console to set up user access to your estimates and standard databases.

For more information on setting up SQL Server security for Sage Estimating, see "G. Set Up Estimating Security" (page 23).

Setting Firewall Exceptions

If you experience communication issues with a remote SQL Server instance, you may be using a firewall that is set up to block network traffic between your computer and the SQL Server instance. To allow communication, you need to set two firewall exceptions:

- The SQL Server Database Engine service. (You need to set a SQL Server Database Engine exception for each instance of SQL Server you use with Sage Estimating.)
- The SQL Server browser service

Notes:

- The following instructions apply to Windows Firewall. If you are using another firewall for your system, contact the firewall manufacturer for instructions on setting service exceptions.
- If you are using SQL Server on a workgroup server, you must set separate firewall exceptions to allow your workstations to communicate with the SQL Server instance. Refer to [Setting the Firewall for Workgroups](#) instructions.
- Sage recommends contacting your system administrator if you need to change firewall settings.

Setting the SQL Server Database Engine exception

1. Determine the path to your SQL Server computer.
2. On the computer or server where SQL Server is installed, open the SQL Server Configuration Manager.

3. Start the SQL Server Configuration Manager.

In Windows 7: Click **Start > All Programs > Microsoft SQL Server > Configuration Tools > SQL Server Configuration Manager**.

In Windows 8.1 or Windows 10: Click **Start > All apps > Microsoft SQL Server > SQL Server Configuration Manager**.

The SQL Server Configuration Manager opens.

4. In the left-hand pane of the SQL Server Configuration Manager, select **SQL Server Services**.
5. In the right-hand pane, right-click on **SQL Server (INSTANCE)**, where (INSTANCE) is the SQL Server instance for which you are creating the firewall exception, and select **Properties**.
6. In the **SQL Server Properties** window, click the **Service** tab.
7. In the **Binary Path** entry, note or record the path described within the quotation marks. This is the file path to the SQL Server instance binary files (the path is contained only within the quotation marks—ignore the text outside the quotes).
8. Open Windows Firewall.

If you are using Windows 7, select **Start > Control Panel > System and Security > Administrative Tools > Windows Firewall with Advanced Settings**.

If you are using Windows 8.1 or Windows 10, select **Start > All apps > Windows System > Control Panel > System and Security > Administrative Tools > Windows Firewall > Advanced Settings**.

- a. In the left-hand pane of the **Windows Firewall with Advanced Security** window, right-click **Inbound Rules**, and then select **New Rule**.
- b. In the **New Inbound Rule** wizard, select the **Program** option, and then click **[Next]**.
- c. Select the **This program path** option.
- d. Click **[Browse]** and locate the **sqlservr.exe** file at the binary file path you recorded in step 1, and then click **[Open]**.
- e. Select the **Allow the connection** option, and then click **[Next]**.
- f. Select the **Domain**, **Public**, and **Private** check boxes, and then click **[Next]**.
- g. Type the name of your SQL Server instance in the **Name** box.
- h. Click **[Finish]** to create the firewall exception for the SQL Server Database Engine service.

The **Windows Firewall with Advanced Security** window opens.

Setting the SQL Server browser service exception

1. Open Windows Firewall.

If you are using Windows 7, select **Start > Control Panel > System and Security > Administrative Tools > Windows Firewall with Advanced Settings**.

If you are using Windows 8.1 or Windows 10, select **Start > All apps > Windows System > Control Panel > System and Security > Administrative Tools > Windows Firewall > Advanced Settings**.

2. In the left-hand pane of the **Windows Firewall with Advanced Security** window, right-click **Inbound Rules**, and then select **New Rule**.
3. In the **New Inbound Rule** wizard, select the **Port** option, and then click **[Next]**.
4. Select **UDP** as the protocol type.
5. Select the **Specific local ports** option, and then type 1434 in the corresponding box.
6. Click **[Next]**.
7. Select the **Allow the connection** option, and then click **[Next]**.
8. Select the **Domain**, **Public**, and **Private** check boxes, and then click **[Next]**.
9. Type `SQL Server Browser Exception` in the **Name** box.
10. Click **[Finish]** to create the firewall exception for the SQL Server browser service.

Setting the Firewall for Workgroups

If you are using SQL Server with a workgroup, you must set the firewall on the workgroup server to allow workstation computers to connect to the instance.

Note: If you are using SQL Server on a domain-based server, you may still need to configure your firewall to allow remote communication. Refer to the *SQL Server Guide* for instructions.

Firewall Settings (Windows 7, Windows 8.1, and Windows 10)

1. Open Windows Firewall.
 - **In Windows 7:** Click **Start > Control Panel > System and Security > Windows Firewall > Advanced Settings**.
 - **Windows 8.1 or Windows 10:** Click **Start > Windows System > Control Panel > System and Security > Windows Firewall > Advanced Settings**.

2. Set rules for inbound and outbound TCP connections:
 - a. Right-click **Inbound Rules**, and then select **New Rule**.
 - b. In the **Inbound Rule** wizard, select **Port**, and then click **[Next]**.
 - c. Select **TCP**, and then select **Specific local ports**.
 - d. In the **Specific local ports** box, type 8005, 49385, and then click **[Next]**.
 - e. Select **Allow the connection**, and then click **[Next]**.
 - f. Select the **Domain**, **Private**, and **Public** check boxes, and then click **[Next]**.
 - g. In the **Name** box, type **Sage Estimating Service** (or other appropriate name), and then click **[Finish]**.
 - h. Repeat steps a through g for outbound TCP connections, selecting **Outbound Rules** in step a.
3. Set rules for inbound and outbound UDP connections:
 - a. Right-click **Inbound Rules**, and then select **New Rule**.
 - b. In the **Inbound Rule** wizard, select **Port**, and then click **[Next]**.
 - c. Select **UDP**, and then select **Specific local ports**.
 - d. In the **Specific local ports** box, type 1433, 1434, and then click **[Next]**.
 - e. Select **Allow the connection**, and then click **[Next]**.
 - f. Select the **Domain**, **Private**, and **Public** check boxes, and then click **[Next]**.
 - g. In the **Name** box, type **Sage Estimating Service** (or other appropriate name), and then click **[Finish]**.
 - h. Repeat steps a through g for outbound UDP connections, selecting **Outbound Rules** in step a.

Additional Recommendations

To ensure accurate performance, Sage **strongly** recommends making changes and verifications to the following settings in SQL Server Management Studio and SQL Server Configuration Manager. Failure to make these changes may result in poor Sage Estimating performance or communication difficulties between Sage Estimating and your SQL Server instance.

Memory

Determine the amount of available memory on the server or workstation where SQL Server is installed. To prevent SQL Server from consuming all available memory, use SQL Server Management Studio to set the maximum amount of memory (in the instance properties) to a reasonable limit (such as 4 GB) as follows:

1. Right-click the SQL Server instance, and then select **Properties**.
2. In the Server Properties window, click **Memory** (left-hand pane).
3. Set the **Maximum server memory** amount to **4000** (or whatever limit you determine).

Recovery Model

Sage recommends that you use the Simple recovery model for your Estimating database.

During the upgrade process, the program now shrinks the existing log file, which can become very large, and it removes invalid estimates. However, it does so only if the database recovery model is set to Simple in the SQL Server software. We do not recommend that you change the recovery model unless your business requires features available only in a different model.

Communication Protocol


Set the communication protocol settings for the Sage Estimating SQL Server instance as follows:

1. Start the SQL Server Configuration Manager.
 - In Windows 7: Click **Start > All Programs > Microsoft SQL Server > Configuration Tools > SQL Server Configuration Manager**.
 - In Windows 8.1 or Windows 10: Click **Start > All apps > Microsoft SQL Server > SQL Server Configuration Manager**.
2. In the left-hand pane of the **SQL Server Configuration Manager** window, click the arrow next to **SQL Server Network Configuration** to display all local SQL Server instances.
3. Select the instance associated with Sage Estimating (**SAGE_ESTIMATING**, by default).
4. In the right-hand pane right-click a communication protocol, and then select **Disable**.
5. Repeat step 4 for all communication protocols *except TCP/IP*. Leave this protocol **Enabled**.
6. In the left-hand pane of the **SQL Server Configuration Manager** window, click the arrow next to **SQL Native Client 10.0 Configuration**.
7. Click **Client Protocols** (left-hand pane).
8. In the right-hand pane right-click a communication protocol, and then select **Disable**.
9. Repeat step 8 for all communication protocols *except TCP/IP*. Leave this protocol **Enabled**.
10. Close the SQL Server Configuration Manager and restart the service.


Copying Databases from Other Instances

Sage Estimating allows the use of just one active SQL Server instance at a time. This instance is a "closed" SQL Server instance. Sage Estimating does not recognize databases (Address Book or standard

databases) transferred or copied from other SQL Server instances unless they are added by way of the **Search For** feature in the Estimating Management Console.

For example, if you have two Sage Estimating installs, Install A and Install B, you cannot copy Address Book databases by copying them from Install A's SQL Server instance to Install B's SQL Server instance alone (using SQL Server Management Studio's built-in Copy Databases wizard, for example). You must also open the Estimating Management Console and use the **Search For**  button in the Address Book Companies/Contacts toolbar.

Copying Databases From One SQL Server Instance to Another



Any database you add to an instance must have the same Sage Estimating version as the other operating databases. For example, if you are using Sage Estimating 19.12, and you want to add a standard database from a previous Sage Estimating installation, upgrade the standard database to version 19.12 before adding it to the new instance. Refer to the Estimating Management Console in-product Help for instructions on using the **Search For** feature.

You can switch active SQL Server instances at any time for Sage Estimating by starting the Configuration wizard, selecting **Server** from the left-hand pane, and clicking **[Change]** from the right-hand pane.

Chapter 6: Managing Your License

This chapter provides detailed information about the Sage online licensing system.

About the License Server and the Sage Online Licensing System

When you activate your product license on the license server, your Sage products and features are registered on and managed from that computer. As you purchase or remove licenses, the Sage online licensing system updates this information on your License Server.

The license server communicates with Sage daily, keeping your licenses up to date automatically.

You can view your licenses and (if necessary) update registration information manually using the License Administration window. The License Administration window displays the number of license uses for the CORE Estimating product, and it lists any additional modules and features you have purchased.

By default, all license uses are allocated to your Sage license server. The Sage license server then provides license uses to individual computers on your network.

Sage Estimating and the Sage License Server

You must have a license to use Sage Estimating. You acquire a license use from the license server when you start Sage Estimating on your workstation. Therefore, the computers running Sage Estimating software must be connected to the Sage license server

The license server keeps track of the products, features, and number of license uses that are available to you and other users, and will make a license available to you, unless all the licenses are currently being used.

If you need to use Sage Estimating while you are not connected to the Internet (for example, when you are away from the office), you can check out a license for offline use. For more information, see "Checking Out a License for Offline Use" (page 52).

Note: In previous versions of Sage Estimating, licenses were managed using a physical dongle. This hardware is no longer required.

Estimating Modules and License Uses

Used as a standalone application, the CORE Sage Estimating (SQL) is a powerful, flexible tool for

estimating all types of construction projects.

You can also purchase the following add-on modules to extend the functionality of Sage Estimating to suit the needs of your business:

- **Crews**
- **Models**
- **Advanced Reporting**, which includes the Comparison Report, the Variance Report, and Custom Reports.
- **eTakeoff**

Note: These modules are licensed separately from the CORE Sage Estimating product. Certain capabilities, menus, and icons described in help are available only if you have purchased the associated module. Contact your Sage sales representative for more information about modules and feature bundles.

General Licensing Steps

After installing Sage Estimating (SQL) on a server and individual workstations, you:

1. Configure your License Server using the **License Administration** window.
 - Designate a computer on your network or workgroup as the Sage license server.
 - On the License Server, enter and send registration information to Sage to activate the licenses for the products and features you have purchased.
2. Connect individual workstations that will run Sage Estimating (SQL) to the Sage license server using the **Configuration Wizard**.

The following sections describe these steps in more detail.

Designating a Sage License Server

One of your first tasks when setting up your Sage Estimating system is to designate a computer on your network to act as your Sage license server.

When deciding which computer to use as the Sage license server, keep in mind that the Sage license server must:

- Remain connected to the Internet for daily validation of licenses.
- Be available continuously to other network computers running Sage Estimating, so that they can acquire licenses for your Sage Estimating products.

Tip: In some situations, you may need to designate more than one computer as a license server. For information about allocating licenses to multiple servers, see "Multiserver Licensing" (page 49).

When you designate a computer as a license server, you must supply the full name of the computer you want to use as the license server. (Alternatively, you can supply its IP address.)

To determine the computer name of the server:

1. Open the Windows **Control Panel**.
 - In Windows 7, click **Start > Control Panel**.
 - In Windows 8 and Windows 10, on the Start menu, click **All Apps > Windows System > Control Panel**.
2. From the Control Panel, click **System and Security > System** to display the **System Properties** window.
3. Under **Computer name, domain, and workgroup settings**, locate **Full computer name**, and then make a note of the name.
4. Close the Control Panel.

To designate the Sage license server:

Important! License uses are allocated to the designated computer when you submit your registration and activate your licenses. If you need to move your Sage Estimating (SQL) server to a different server, later, you must first deauthorize the licenses on the **License Information** tab on the old server before you can activate them on a new server.

1. On the computer where you plan to activate your license, start **License Administration**.
2. Click **Change server**.
3. In the **Specify License Server** window:
 - a. In the **Computer** box, enter the name of the computer running the license server.
 - b. In the **Port number** box, type **48650** if that is not the port number displayed in the box.
4. Click **[OK]**.

Registering the Software and Activating Licenses

To activate your license:

1. On the machine designated as your license server, open the **License Administration** window.

Click **Start > All Apps > Sage Estimating > License Administration**.

2. Check that computer named in the **License server** box is the designated license server.

If License Administration is not pointing to the correct server, click **Change server**, and then enter the correct computer name or IP address of your license server.

3. In the Registration Information section, submit your registration details as follows:

- a. Click the **Edit registration information** link.
- b. In the **Sage client ID** box, type your client number.
- c. In the **Registration name** box, type your registered company name exactly as provided by Sage.
- d. Click **[OK]**

If the activation was successful, the Licensed Modules grid displays the modules and number of uses that you have purchased. Your license server is now ready to serve licenses to your Sage Estimating (SQL) users.

If the activation was successful, the Licensed Modules grid displays the modules that you have purchased.

Connecting to the License Server from Sage Estimating

Before you can use Sage Estimating on a client workstation, you must connect the workstation to your Sage license server. Then, when you start Sage Estimating, the program automatically acquires a license use for the workstation.

To connect to the license server:

1. On your workstation, open the **Specify License Server** window:

- a. Start the **Estimating Configuration Wizard**.
- b. In the navigation pane, click **Licensing**.

- c. In the right-hand panel, select the **License Server** option.
 - d. Click **[Change]**.
2. In the **Specify License Server** window:
 - a. In the **Server** box, enter the name of the computer running the license server.
 - b. In the **Port** box, type **48650** if that is not the port number displayed in the box.
3. Click **[OK]**.

Updating License Information

The Sage license server automatically retrieves license information from Sage every day. The licenses give you access to the various modules of Sage Estimating (SQL). As you purchase or remove license activations, the license server automatically updates this information in your system.

You can also update the licensing information manually, as follows:

1. Open **License Administration**.
2. Ensure that License Administration tool is pointing to your designated License Server machine.
3. On the License information tab, click the **Update license information** link.

Your Sage license server then contacts the Sage online licensing system to update your license information, as needed.

Deauthorizing a License Server

When you set up your Sage license server, the Sage online licensing system allocates the licenses for your purchased Sage Estimating modules and license uses to that computer.

At some point in the future, you might need to designate a different computer as the license server (for example, if you want to upgrade the server to a new computer) or change your registered company name. However, you cannot allocate licenses to a new computer or a new company while they are allocated to the original server.

Before you can reallocate your licenses to a different license server, you must release the allocated licenses to the Sage online licensing system. You do so by deauthorizing the original license server, enabling you to configure the new license server and register the licenses to that machine.

Caution! Do not deauthorize your license server if any users are working with Sage Estimating programs or have license uses checked out. Doing so can lock the licenses, requiring Sage Customer Support to resolve.

To deauthorize your Sage license server:

1. Check your current license server information:
 - a. Start **License Administration**.
 - b. Ensure that the **License server** box contains the name of the computer you want to deauthorize.
2. Deauthorize your current license server:
 - a. Ensure that no other users are working with Sage Estimating.
 - b. Click **Deauthorize license server**.

You should receive a message saying that deauthorization was successful.

Changing Your Company's Registration Information

Caution! Do not change registration information if any users are working with Sage Estimating programs or have license uses checked out. Doing so can lock the licenses, requiring Sage Customer Support to resolve.

To change your registration information:

1. Deauthorize your current license server.

Important! This step is crucial. You must release your allocated licenses to the Sage online licensing system so that they are available to reallocate to the "new" company. Make sure you receive a message saying that deauthorization was successful before you proceed.

2. Change your company's registration name:
 - a. Click **Edit registration information**.
 - b. Enter your new registration information in the Sage client ID and Registration name boxes.
 - c. Click **[OK]**.

If the new registration is successful, the Licensed Modules grid displays your licensed modules and license uses with your new registration information.

Note: If you are using licensed standard databases, you need to obtain new activation codes for these databases after changing your registration information.

Moving Your Sage License Server to Another Computer

Caution! Do not try to change your license server if any users are working with Sage Estimating programs or have license uses checked out. Doing so can lock the licenses, requiring Sage Customer Support to resolve.

To move your license server to another computer.

1. Verify the full computer name of the computer you want to use as the new license server.
2. Deauthorize your current license server.

Important! This step is crucial. You must release your allocated licenses to the Sage online licensing system so that they are available to reallocate to the server. Make sure you receive a message saying that deauthorization was successful before you proceed.

3. Click **Change server**, and then, in the **Specify License Server** window:
 - a. In the **Computer** box, type the full name of the computer you want to use as the license server.
 - b. Click [OK].

Important! Entering a new computer name in the Specify License Server window points the License Administration window to a different machine, enabling you to administer licenses on that license server.

4. To update your registration information, click **Edit registration information**, type your Sage client ID and registration name in the boxes provided, and then click [OK].

If the new server is authorized successfully, the Licensed Modules grid displays your licensed modules and license uses with your new registration information.

Note: After changing the license server, you will need to reconfigure each Estimating workstation to point to the new license server.

Multiserver Licensing

If you need to administer your company's licenses from two or more license servers, you can allocate licenses manually to different computers.

Allocating licenses to multiple servers involves two main tasks:

1. You reduce the total number of license uses allocated to the original license server, releasing some license uses.
2. You point to a second license server, and then allocate the remaining license uses to that server.

You use the Multi-Server License Administration window to reallocate license uses to secondary license servers.

Example: Your company has purchased a license for Sage Estimating with 10 license uses. You want to allocate 8 of those uses to your main server and 2 uses to a server at your satellite office.

The following steps assume that you have an active license server with 10 uses.

To reduce the license uses allocated to the original license server:

1. Start **License Administration**.
2. Ensure that the **License server** box contains the name of your designated license server.
3. On the License information tab, click **Multi-server licensing**.

The Multi-Server License Administration window appears, with the total number of license uses allocated to this server by default.

4. Select **Manually specify license allocations for this server**.

This step enables you to change the number of license uses for the current license server.

Module name	Total uses	Available uses	Uses for <machine name>
Core	100	0	10
Advanced Reporting	unlimited	unlimited	unlimited
Crews	unlimited	unlimited	unlimited
ePlan Takeoff	unlimited	unlimited	unlimited
Models	unlimited	unlimited	unlimited

5. In the **Uses for <machine name>** box, type the number of uses you want to allocate to the current

server.

In our example, allocating eight license uses to the current server releases two uses that can be allocated to a second server.

6. Click **[OK]**.

Note: You must have access to the secondary license server and connect to it in the following task.

To allocate residual licenses to a different server:

1. In the License Administration window, connect to the secondary license server:
 - a. Click **Change server**.
 - b. In the Specify License Server window, type the full computer name (or IP address) of that server.
2. Click **Edit registration information**.
3. In the Registration Information window, enter the same Sage client ID and registration name used on the original server.
4. Click **[OK]**.

The Licensed Modules grid displays your purchased modules, and shows the residual license uses that allocated to this server.

Monitoring License Use

You use the License Administration window to view license uses, the users who are logged on to Sage Estimating, and the licensing events for the current license server—that is, the computer specified in the **License server** box.

- To view which users are logged on to Sage Estimating, click the **Active users** tab.
- To view checked-out licenses, click the **License information** tab.
- To view the results of license update attempts, click the **Event log** tab.
- Click **Clear event log** if you no longer need the information.

Viewing licenses for a different license server

Initially, the current license server is the one on which you activated your licenses. If you allocated license uses to another Sage license server and you want to view activity for that server, you "point" the License Administration window to that server, as follows:

1. In the License Administration window, click **Change server**.
2. In the Specify License Server window, enter the computer name and port number for the secondary server.

Checking Out a License for Offline Use

If you anticipate a need to use Sage Estimating when your computer cannot communicate with the license server, you can check out a license use from the Sage license server while you are still connected.

Important! Checking out a product license use removes it from the license server's pool of available license uses and places it directly on the computer checking out the license. Because checking out a license may prevent other users' access to Sage Estimating, you should check out a license only when necessary, and check it back in promptly when you are reconnected to your network.

Before checking out a license

To work offline, you must take additional steps besides checking out a license. For example, you must have a local SQL Server instance that contains an estimates database, as well as copies of your standard database and address book if needed.

You also require a backup copy of any estimates (exported from your server) that you plan to work with while you are offline. You import those estimates into your local estimates database.

Also, if you are using Sage Estimating in a workgroup environment, you must change the Sage Estimating Licensing Service to run under your local system account. For more information, see the section, "Running the Sage Estimating Licensing Service under Your Local User Account" (page 53).

To check out a license use:

1. In the Sage Estimating main window, click **File > Check Out License**.
2. Click **[Yes]**.

Note: If you check out a license use, it remains checked out on this computer until you check in the license using **Check In License** from the File menu.

To check in a license use:

1. In the Sage Estimating main window, click **File > Check In License**.
2. Click **[Yes]**.

Running the Sage Estimating Licensing Service under Your Local User Account

Sage Estimating operates in two kinds of environments:

- **Domain-controlled**, which uses a secure and centralized network authentication protocol.
- **Workgroups**, which use an older type of authentication that is not centralized. (This includes hosted environments, such as Azure, with multiple machines networked in the cloud).

In a domain environment, checking out a license works automatically. You do not need to change the Sage Estimating Licensing Service before you check out a license.

However, in a workgroup environment, checking out a license is not automatic because the default security protocol does not work in a decentralized environment with anonymous users. Therefore, when configuring Sage Estimating to run in a workgroup environment, you need to set up the Sage Estimating Licensing Service to run under your local user account on your computer:

To set up the licensing service to run under your local user account:

1. In Windows **Services**, right-click **Sage Estimating Licensing Service 4.6**, then click **Properties**.
2. Click the **Log On** tab.
3. In the **This account** box, type your user account ID for your local machine .
4. In the **Password** and **Confirm Password** boxes, type the password for your local account.
5. Click **[Apply]**.
6. Click **[OK]**.
7. Restart the Sage Estimating Licensing Service.

Troubleshooting License Server Issues

This section provides suggestions to resolve some of the common issues that can occur with your Sage Sage Estimating (SQL) licenses.

The Registration Information Does Not Match

The **Sage client ID** and **Registration Name** on the License Administration window must match the information on the Sage license server. Ensure the information is entered correctly here.

You Exceeded Your License Activations

You do not have enough licenses to support everyone attempting to use Sage Estimating. You may want to purchase more licenses.

Tip: The **Number of requests which exceeded use count** box on the License information tab of the License Administration window displays the number of times in the last three months that requests for licenses have exceeded the number of licenses available.

Disconnection from the Network

Note: This information does not apply if you are running Sage Estimating and the Sage license server on one computer as a stand-alone installation.

If a workstation is disconnected from the Sage license server while you are using the License Administration window or the Configuration Wizard, the system displays a **Disconnected from the License Server** message.

Since our products run on your company's network, it is important to maintain the network connection between workstations and the Sage license server. When your workstation is disconnected from the Sage license server, you cannot connect the workstation to the license server or perform license administration functions from the workstation.

To reconnect to the license server:

1. Wait a few minutes, and then try again to use the Configuration Wizard.
2. If the workstation is still disconnected, check whether the network cable is unplugged.
3. If the workstation remains disconnected, check whether a network drive is disconnected.
4. Contact your network administrator.

When you have restored your connection to the Sage license server, you can use the License Administration window and the Configuration Wizard to perform licensing tasks.

Connectivity across Your Network

To run Sage Estimating, client workstations must be connected to the Sage license server and to the computer that hosts the SQL Server instance you are using for Sage Estimating.

If only one user sees the “Sage Estimating (SQL) can’t communicate with the designated Sage license server” message when all other users are connected, you know that the connectivity problem is limited to that one person.

If you encounter a hardware failure with your license server, no one can run Sage Estimating.

Disconnected Network Drive

When your workstation is disconnected from the network drive for the Sage license server, you cannot perform license administration functions from the workstation.

To check whether a network drive is disconnected:

1. Click **[Start] > My Computer**.
2. In the Network Drives section, check the Type column for the network drive for the Sage license server.
3. If the Type is Disconnected Network Drive, select the network drive and then select another network drive.
4. If the Type changes to Network Drive, try to use the Configuration Wizard.
5. If the Type remains Disconnected Network Drive, contact your network administrator.

Network Cable Unplugged

When the network cable is unplugged from your workstation, you cannot perform license administration functions using the License Administration tool.

To check whether a network cable is unplugged:

1. Check the notification area, at the far right of the taskbar, for the message **A network cable is unplugged**.
 - If you see this message, reconnect the network cable to the workstation.
 - If you do not see this message, check the network connections:
 - a. Click **[Start > Control Panel > Network Connections**.
 - b. In the LAN or High-Speed Internet section, check the Status of the Local Area Connection.
 - If the Status is **Network cable unplugged**, reconnect the network cable to the workstation.
 - If the Status is **Connected**, the network cable is connected to the workstation.
2. Try to use the License Administration tool.

Windows "Sleep Mode" Prevents Computers from Obtaining a License Use

If the computer you are using as your license server goes into sleep mode, other computers on the network cannot obtain a license.

Set **Sleep Mode** on your license server computer to **Never**.

To set the Sleep Mode to “Never”:

- **For Windows Windows 7 and Server 2008 R2:**
 1. **Start > Control Panel > System and Security > Power Options.**
 2. Select **Change when computer sleeps.**
 3. From the **Put computer to sleep** list, select **Never.**
- **For Windows 8.1 Professional, Windows 10, and Server 2012 Standard:**
 1. **Start > All apps > Control Panel > System and Security > Power Options.**
 2. Select **Change when computer sleeps.**
 3. From the **Put computer to sleep** list, select **Never.**

Index

A

- activating Estimating products 20
- activation 20
- addon modules
 - licenses for 43
- Advanced Reporting
 - license 43
- assigning database permissions 37
- authentication mode 36

B

- backup Pervasive data 32

C

- collation settings 36
- Common Language Runtime 28
 - turning off after upgrading 28
- computer name
 - determine 45
- Configuration Tools 9
- Configuration Wizard
 - using to connect to Sage license server 46
- contacting Sage 6

Crews

- license 43

D

- data migration
 - overview 29
 - prerequisites 31
 - process 31
- database permissions 37
- database structure 29
- databases
 - migrating preexisting data 29
- deauthorizing a license server 47

E

- Estimating CORE
 - license 43
- eTakeoff
 - license 43
- exceptions, firewall 37

F

- firewall, workgroup exceptions 37
- folder control requirements 12

H

help

- using the in-product Help 3

I

installation

- activating Estimating products 20
- collation settings 36
- Estimating products 17
- scenarios 15
- SQL Server Express 18
- terminal server 28

- installing Estimating products 17

- installing SQL Server Express 18

L

License Administration

- overview 43

- license server 46

- license use 43

license uses

- allocating to multiple servers 49

- licenses 46

- activating licenses 46

M

migration

- overview 29

- prerequisites 31

- process 31

- mixed mode authentication 36

Models

- license 43

- modifying existing instances 34

- multiserver licensing 49

N

network 54-55

- connectivity 54

- disconnected 54

- disconnected network drive 54

- network cable 55

- unplugged 55

O

OST integration

- license 43

P

- PEBackup folders 32

- prerequisites, data migration 31

R

- Recovery Model 41

- registry keys 13

requirements

- folder control 12

S

Sage contact information 6

Sage license server 43

- about 43, 46

- name 45

scan, data folder

- restarting 32

- stopping 32

SQL Server

- installing SQL Server Express 18

- modifying existing instances 34

- selecting a new instance 42

SQL Server Common Language Runtime

- turning off after upgrading 28

T

terminal server installation 28

Troubleshooting

- turning off Windows sleep mode 55

U

upgrade paths 14

W

Windows authentication 36

Windows sleep mode

- prevents obtaining a license 55

- turning off 55